



## Installation **LuArtX CarF** license server

When you have purchased a LuArtX\_18.lic, you need to install the LuArtX license server.

After you have already installed the CarF factory planning software, you find the folder «dienste».



In this folder you do find the LuArtX license server.



Open the «LuArtX\_Licman.exe» with double click.

Choose the installation language.




Define the installation path for the license server.



This path is used to install the license server and the files «[luartx\\_licman\\_lic.lic](#)» and «[luartx\\_18.lic](#)» will be saved there. These files are needed to run the CarF factory planning modules!

Example:

- Installation path: `c:/install/Licman_install/licman/`  
Shared folder, all computers / notebook must have access to this folder  
[c:/install/Licman\\_install/licman/license](#)




Name	Änderungsdatum	Typ	Größe
luartx_18.lic	02.05.2019 09:46	LIC-Datei	
luartx_lic_man.ini	04.05.2019 12:15	Konfigurationseinstell...	
luartx_lic_server.cfg	04.05.2019 12:15	Bentley MicroStation-...	
luartx_licman_1905.log	04.05.2019 12:17	Textdokument	
luartx_licman_lic.lic	04.05.2019 12:18	LIC-Datei	



Create Shared for the installation.

IMPORTANT: for the CarF Modules you need to use **licman\_lx**.

You cannot use the same logical as for VENTURIS!



The «share» can be shown over **> net share**

```
C:\venturis>cd ..
C:\>net share

Name                Ressource                Beschreibung
-----
ADMIN$              C:\WINDOWS               Remoteverwaltung
C$                  C:\                       Standardfreigabe
D$                  D:\                       Standardfreigabe
E$                  E:\                       Standardfreigabe
IPC$                C:\                       Remote-IPC
licman$             C:\Venturis\licman\license Benutzt von TRICAD-MS Licman
licman_lx$         C:\Program Files (x86)\Luartx\Licman\license Benutzt von LUARTX Lizenz Server
tmp                 C:\tmp
Users               C:\Users
Der Befehl wurde erfolgreich ausgeführt.
```


➔ //HOST/licman\_lx\$

Here you can define, for how long the Logfile shall be saved.


→ Example, each month a new one ... otherwise it will be too long!

There is always a possibility that you receive an error message.... Network fail, MicroStation Crash, etc.


→ Example, all licenses will be released at 3 in the morning.




→further




→further.....





→further



→install....





You are asked to choose your «Luartx\_18.lic» license file. This file will be copied in the installation of the license server.





The LuArtX license server is now installed.



The installation saved the environment variable «LUARTX\_LIC\_MAN». Over this variable the «LUARTX License Service 1.0» finds the license files.



Windows (C:) > install > licman\_install > licman > license

Name	Änderungsdatum	Typ	Größe
luartx_18.lic	02.05.2019 09:46	LIC-Datei	
luartx_lic_man.ini	04.05.2019 12:15	Konfigurationseinstell...	
luartx_lic_server.cfg	04.05.2019 12:15	Bentley MicroStation-...	
luartx_licman_1905.log	04.05.2019 12:17	Textdokument	
luartx_licman_lic.lic	04.05.2019 12:18	LIC-Datei	

## WINDOWS:

Variable in «SYSTEM» in

The screenshot shows the Windows System Properties dialog box with the 'Umgebungsvariablen' (Environment Variables) tab selected. The 'Systemvariablen' (System variables) list is visible, with 'LUARTX\_LIC\_MAN' highlighted. The value for this variable is 'C:\install\licman\_install\licman\license'. The 'Benutzervariablen für esthi' (User variables for esthi) section is currently empty.

Variable	Wert
ComSpec	C:\Windows\system32\cmd.exe
configsetroot	C:\Windows\ConfigSetRoot
DriverData	C:\Windows\System32\Drivers\DriverData
LUARTX_LIC_MAN	C:\install\licman_install\licman\license
NUMBER_OF_PROCESSORS	8
OS	Windows_NT
Path	C:\Windows\system32;C:\Windows\C:\Windows\System32\Wbe...
PATHEXT	.COM;.EXE;.BAT;.CMD;.VBS;.VBE;.JS;.JSE;.WSF;.WSH;.MSC





**MicroStation:**

The environment variable «**LUARTX\_LIC**» must be set.

**LUARTX\_LIC** defines the folder, where the licence file **luartx\_18.lic** is saved.

